

Setting	MSI key / Command line parameter	JSON identifier	Value type	Valid values	Note
Flip video	sfmirror	selfViewMirror	bool	true/false	
Do not show self-view when the camera is turned off in the application	videomute	disableSelfViewOnBlind	bool	true/false	
Invert X-axis PTZ camera control	invertptz	invertedPTZControl	bool	true/false	
Speaker volume	aplaylevel	audioPlayLevel	double	[0; 1]	Don't use with Automatic gain control
Microphone volume	acapturelevel	audioCapterLevel			
Echo cancellation	aec	aecEnable	bool	true/false	
Automatic gain control	agc	agcEnable	bool	true/false	
Noise suppression	ns	noiseSupEnable	bool	true/false	
Enable diagnostic audio dump	adump	audioDumpEnable	bool	true/false	
Control app with HID device buttons	hwhid	isSpeakerphoneHardwareMuted	bool	true/false	
Connection server	server	userDefinedServerHost	string		

Server connection port	port	userDefinedServerPort	int		
Server connection	corpserver	corporateServer	bool	true	Connection to a corporate server, which is specified in server parameter
				false	Connection to TCO, this parameter is ignored if server is specified
Suppress direct server connection	forbiddc	forbidDirectConnection	bool	true/false	
Check for available server connections upon launch	asksrv	canAskForServerSelect or	bool	true/false	
Use proxy system settings	sysproxy	useSystemProxy	bool	true/false	

User limits	userbitrate	userDefinedBitrate	int	0	User bitrate
				1	Modem
				2	ADSL
				3	Wi-Fi
				4	Ethernet
				5	Maximum
Input bitrate	inbandwidth	inputBandWidth	int	[32, 10240]	These settings should be used simultaneously while the parameter userbitrate should be either left unspecified or set to 0
Output bitrate	outbandwidth	outputBandWidth	int		
Upload limits	uplimit	uploadLimit	int	[1; 100]	
Download limits	dwnlimit	downloadLimit	int		
Sign in automatically	autologin	enableAutologin	bool	true/false	
Allow the “Rate application” pop-up to be displayed	askrateus	canAskForRateUs	bool	true/false	When enabled, the rating window won’t be displayed after calls/conferences

Language	lang	language	string	ru	Russian
				en	English
				de	German
				it	Italian
				cs	Czech
				es	Spanish
				fr	French
				pl	Polish
				tr	Turkish
				pt	Portuguese
				az	Azerbaijani
				uk	Ukrainian
				zht	Chinese (Traditional)
				zh	Chinese (Simplified)
				vi	Vietnamese
				ko	Korean
ja	Japanese				
he	Hebrew				

				ar	Arabic
Hide camera error messages	hidecamerr	cameraErrorsHidden	bool	true/false	When parameter is enabled, an icon indicating a camera error will be displayed, clicking on this icon will expand the error message
Automatically hide the names of idle conference participants	hidedn	hideDnByTimeout	bool	true/false	
Minimize app to the tray when closing	tray	leaveAppRunningInTray	bool	true/false	
Launch automatically at system startup	autorun	enableAutoStart	bool	true/false	
Minimal rate of video area render update	minfps	minRenderFrameRate	int	[0; 60]	The minimal rate should not exceed the maximal rate
Maximal rate of video area render update	maxfps	maxRenderFrameRate	int	[0; 60]	The maximum rate should not be lower than the minimum rate