

No	Name	MSI key	JSON key	Type	Allowed values	Notes
Supported in 8.3.0						
1	Mirror the self-view	sfmirror	selfViewMirror	bool	true/false	
2	Don't show the camera video when the camera is turned off at the software level	videomute	disableSelfViewOnBlind	bool	true/false	
3	Invert PTZ camera control along the X-axis	invertptz	invertedPTZControl	bool	true/false	
4	Audio playback volume level	aplaylevel	audioPlayLevel	float	[0; 1]	
5	Audio capture level	acapturelevel	audioCapterLevel	float	[0; 1]	
6	Echo cancellation	aec	aecEnable	bool	true/false	
7	Automatic gain control	agc	agcEnable	bool	true/false	
8	Noise suppression	ns	noiseSupEnable	bool	true/false	
9	Create dump files for audio diagnostics	adump	audioDumpEnable	bool	true/false	
10	Control the application with hardware buttons of HID devices	hwhid	allowHIDControl	bool	true/false	
11	The server to be connected to	server	userDefinedServerHost	string		
12	The server port to be used for connection	port	userDefinedServerPort	int		
13	Server connection	corpserver	corporateServer	bool	true	Connecting to a corporate server that needs to be specified via userDefinedServerHost
					false	Connecting to TCO, the setting is ignored if userDefinedServerHost is configured
14	Disable direct connection	forbiddc	forbidDirectConnection	bool	true/false	
15	Check if any servers are available when the application is launched	asksrv	canAskForServerSelector	bool	true/false	
16	Use system proxy settings	sysproxy	proxyMode	bool	true/false	
17	User-defined restrictions	userbitrate	userDefinedBitrate	int	0	User-defined bitrate
					1	Modem
					2	ADSL
					3	Wi-Fi
					4	Ethernet
5	Maximum					
18	Inbound bitrate	inbandwidth	inputBandWidth	int	[32, 10240]	These settings have to be used together while the key userDefinedBitrate should be either unspecified or set to "0"
19	Outbound bitrate	outbandwidth	outputBandWidth	int		
20	Upload limit	uplimit	uploadLimit	int	[1; 100]	
21	Download limit	dwnlimit	downloadLimit	int		
22	Automatic authorization	autologin	enableAutologin	bool	true/false	When the setting is enabled, the evaluation window is not displayed after calls/conferences
23	Permission to display the "Rate us" window	askrateus	canAskForRateUs	bool	true/false	

No	Name	MSI key	JSON key	Type	Allowed values	Notes
24	Language	lang	language	string	ru	Russian
					en	English
					de	German
					it	Italian
					cs	Czech
					es	Spanish
					fr	French
					pl	Polish
					tr	Turkish
					pt	Portuguese
					az	Azerbaijani
					uk	Ukrainian
					zht	Chinese (traditional)
					zh	Chinese (simplified)
					vi	Vietnamese
ko	Korean					
ja	Japanese					
he	Hebrew					
ar	Arabian					
25	Hide messages about camera errors	hidecamerr	cameraErrorsHidden	bool	true/false	When the setting is enabled, the camera error icon is displayed, and clicking on the error reveals it
26	Automatically hide participants' names when they are inactive	hidedn	hideDnByTimeout	bool	true/false	
27	Leave the application in the tray after closing	tray	leaveAppRunningInTray	bool	true/false	
28	Automatically launch the application when the OS is started	autorun	enableAutoStart	bool	true/false	
Supported in 8.4.0						
29	Invert Y-axis PTZ camera control	_____	invertedYPTZControl	bool	true/false	
30	Minimum frame rate of animations in the video area and some UI components in the client application	aframerate	animationsFrameRate	int	[0; 60]	The animation frame rate cannot be greater than the maximum frame rate.
31	Maximum frame rate of the video area	maxfps	maxRenderFrameRate	int	[0; 60]	The maximum frame rate cannot be less than the animation frame rate.
32	Power-saving mode	powersavingmode	powerSavingMode	string	Balanced	Balanced power-saving mode
					Maximum saving	Maximum power-saving mode
33	Use power-saving mode	usepowersavingmode	usePowerSavingMode	bool	true/false	Activation of selected power-saving mode
34	Ignore the system scale on Wayland/X11	_____	ignoreSystemScale	bool	true/false	Determines whether the system scale should be ignored on Wayland/X11
Supported in 8.5.0						
35	Content-sharing mode	screensharingmode	lastScreenSharingMode	int	0	Content only
					1	Camera video and content in separate windows
					2	Camera video over the content
					3	Use content as a participant's background

No	Name	MSI key	JSON key	Type	Allowed values	Notes
36	Path to the folder for saving conference recordings	recordfolder	recordSaveFolder	string		
37	Path to the file download folder	filetransferfolder	recordFileTransferFolder	string		
38	Default layout in a group conference	defconfmatrix	defaultMultiConfMatrix	string	One	The layout with only one window
					Even	All windows are of equal size
					BigCorner	In the corner
					BigTop	In the upper part
					BigLeft	On the left
					BigOverlay	Overlay
39	Automatic enlargement of the content window	switchtocontent	switchToSharedContent	bool	true/false	
40	Mode for automatic enlargement of the content window	contentmode	sharedContentBehaviour	int	0	Show in the spotlighted (high-priority) window
					1	Show in the single layout window
					2	Show in a separate application window
41	Change the spotlighted (high-priority) window by voice activity	switchtospeaker	switchToActiveSpeaker	bool	true/false	
42	Hide non-video participants	hideparticipants	hideNonVideoParticipants	bool	true/false	
43	Hide the video area by default if the application is opened in the Contacts and Calls sections	hideframe	framesBoxHidden	bool	true/false	
44	Automatically accept invitations to the podium from moderators	autoacceptpodium	autoAcceptPodiumFromOwner	bool	true/false	
45	Always display the self-view over the general layout	displayselfview	alwaysDisplaySelfView	bool	true/false	
46	Turn on the camera	videoenable	videoEnable	bool	true/false	
47	Unmute the microphone	audiorecordable	audioRecordEnable	bool	true/false	
48	The section which is opened when the client application is started	applicationlayout	lastApplicationLayout	int	1	Chats
					2	Contacts
					3	Conferences
					4	Call history
					5	Slideshows
					6	Video recordings
					7	Not used
					8	Settings
					9	User list
49	Allow local recording of my own media stream	record	record	int	0	Nobody
					1	Ask me each time
					2	Users from my address book
					3	Everyone
50	Allow remote control of my desktop	desktopControl	desktopControl	int	0	Everyone
					1	Ask me each time
					2	Nobody

No	Name	MSI key	JSON key	Type	Allowed values	Notes
51	Show app widget in meetings when the window is inactive	showConferenceWidget	showConferenceWidget	bool	true/false	
52	Enable SSO login	enableSSO	enableSSO	bool	true/false	
Supported in 8.5.3						
53	Enable Multi-Window Mode	enableMultiWindowMode	enableMultiWindowMode	bool	true/false	
54	Additional user details in contact list	additionalInfoType	additionalInfoType	int	0	ID
					1	Network Status
					2	Custom Status
55	Block OS-level audio capture gain control	holdMicVolume	holdMicVolume	bool	true/false	Enabling this option disables AGC