| № | Name | JSON key | MSI key | Type | Allowed values | | Notes |
|---|------|----------|---------|------|----------------|---|-------|
| 1 | Mirror the self-view | selfViewMirror | sfmirror | bool | true/false | | |
| 2 | Don't show the camera video when the camera is turned off at the software level | disableSelfViewOnBlind | videomute | bool | true/false | | |
| 3 | Invert PTZ camera control along the X-axis | invertedPTZControl | invertptz | bool | true/false | | |
| 4 | Audio playback volume level | audioPlayLevel | aplaylevel | double | [0; 1] | | Not to be used together with automatic gain control |
| 5 | Audio capture level | audioCapturerLevel | acapturelevel | double | [0; 1] | | Not to be used together with automatic gain control |
| 6 | Echo cancellation | aecEnable | aec | bool | true/false | | |
| 7 | Automatic gain control | agcEnable | agc | bool | true/false | | |
| 8 | Noise suppression | noiseSupEnable | ns | bool | true/false | | |
| 9 | Create dump files for audio diagnostics | audioDumpEnable | adump | bool | true/false | | |
| 10 | Control the application with hardware buttons of HID devices | allowHIDControl | hwhid | bool | true/false | | |
| 11 | The server to be connected to | userDefinedServerHost | server | string | | | |
| 12 | The server port to be used for connection | userDefinedServerPort | port | int | | | |
| 13 | Server connection | corporateServer | corpserver | bool | true/false | | |
| 14 | Disable direct connection | forbidDirectConnection | forbiddc | bool | true/false | | |
| 15 | Check if any servers are available when the application is launched | canAskForServerSelector | asksrv | bool | true/false | | |
| 16 | Use system proxy settings | useSystemProxy | sysproxy | bool | true/false | | |
| 17 | User-defined restrictions | userDefinedBitrate | userbitrate | int | 0 | User-defined bitrate | |
| | | | | | 1 | Modem | |
| | | | | | 2 | ADSL | |
| | | | | | 3 | Wi-Fi | |
| | | | | | 4 | Ethernet | |
| | | | | | 5 | Maximum | |
| 18 | Inbound bitrate | inputBandWidth | inbandwidth | int | [32, 10240] | | These settings have to be used together while the key |

| 19 | Outbound bitrate | outputBandWidth | outbandwidth | int | [32, 10240] | userDefinedBitrate should be either unspecified or set to "0" |
|---|---|---|---|---|---|---|
| 20 | Upload limit | uploadLimit | uplimit | int | [1; 100] | |
| 21 | Download limit | downloadLimit | dwnlimit | int | | |
| 22 | Automatic authorization | enableAutologin | autologin | bool | true/false | |
| 23 | Permission to display the "Rate us" window | canAskForRateUs | askrateus | bool | true/false | |
| 24 | Language | language | lang | string | ru | Russian |
| | | | | | en | English |
| | | | | | de | German |
| | | | | | it | Italian |
| | | | | | cs | Czech |
| | | | | | es | Spanish |
| | | | | | fr | French |
| | | | | | pl | Polish |
| | | | | | tr | Turkish |
| | | | | | pt | Portuguese |
| | | | | | az | Azerbaijani |
| | | | | | uk | Ukrainian |
| | | | | | zht | Chinese (traditional) |
| | | | | | zh | Chinese (simplified) |
| | | | | | vi | Vietnamese |
| | | | | | ko | Korean |
| | | | | | ja | Japanese |
| 25 | Hide messages about camera errors | cameraErrorsHidden | hidecamerr | bool | true/false | |
| 26 | Automatically hide participants' names when they are inactive | hideDnByTimeout | hidedn | bool | true/false | |
| 27 | Leave the application in the tray after closing | leaveAppRunningInTray | tray | bool | true/false | |
| 28 | Automatically launch the application when the OS is started | enableAutoStart | autorun | bool | true/false | |

| 29 | Minimum frame rate of animations in the video area and some UI components in the client application | animationsFrameRate | aframerate | int | [0; 60] | The animation frame rate cannot be greater than the maximum frame rate. |
|----|----|----|----|----|----|----|
| 30 | Maximum frame rate of the video area | maxRenderFrameRate | maxfps | int | [0; 60] | The maximum frame rate cannot be less than the animation frame rate. |
| 31 | Power-saving mode | powerSavingMode | powersavingmode | string | Balanced | Balanced power-saving mode |
| | | | | | Maximum saving | Maximum power-saving mode |
| 32 | Use power-saving mode | usePowerSavingMode | usepowersavingmode | bool | true/false | Activation of selected power-saving mode |
| 33 | Ignore the system scale on Wayland/X11 | ignoreSystemScale | — | bool | true/false | Determines whether the system scale should be ignored on Wayland/X11 |